

Upgrade instructions Jasmine software V1.1.0 -> V1.1.2

1. Jasmine type specific instruction

The software is intended for Jasmine machines only.



2. Prerequisites:

Save the current software including machine settings before upgrading:

Make a backup of the folder D:\SPG Printer

3. Run Setup – SPG Printer version V1.1.2


- Double click on the “**SPG Printer V1.1.2.exe**” starts the Installation.



→ Click on “*Next*”






- If prompted for a target directory make sure it is **D:\SPG Printer**






→ Click on “*Install*”

- Please wait until the installation is ready.
- Click on “*Finish*” to complete the installation

4. Restore configuration

 scanprnew_en.qm	04-Jul-22 17:05	QIM File	1 KB
 setting.ini	11-Aug-22 15:58	INI File	1 KB
 SlaveEifoSmsv2.ima	16-Dec-15 20:44	Disc Image File	160 KB

Copy the file “setting.ini” from the backup to D:\SPG Printer\ and confirm overwriting.

 CFC	22-Mar-23 10:33	File folder	
 ParamSet	22-Mar-23 10:39	File folder	
 nicture	22-Mar-23 10:33	File folder	

Copy the folder “ParamSet” from the backup to D:\SPG Printer\ and confirm overwriting.

5. Update SPGPrints Look and Feel



Run the installer for TPP, this will re-apply the SPGPrints approved look and feel.

Double click on TPPServer_Setup_1.x.x.exe

